README.md 12/5/2018

Distributed Processing Program

Prerequisite

- 1. java >1.8
- 2. Make sure that java and javac is in path
- 3. Tensor flow (if want to run with simulation off)

Build

1. Run build.bat

Install Tensor flow models

One of the service provided is to run Tensor Flow Object Detection. This will require the tensor flow pre-trained models and labels. To download them run download_models.ps1 . To save time, you can also turn on simulation so that the it does not actually run the tensor flow command but return a hard coded value. See configuration below to find out how to turn it on.

Configuration

If a configuration file is not found. First startup will create default config file.

Tracker

File: tracker.config.properties

| Config | Definition | Default |
|-------------------|------------------|---------|
| rmi_registry_port | Tracker RMI Port | 1099 |

Server

File: server.config.properties

| Config | Definition | Default |
|---------------------------|------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------|
| image_analytics_simulate | Turn simulate on or off see Install Tensor flow models | 0 |
| services | Services that this server will provide. Split by comma (,) | VideoAnalytics,VideoSplit,ImageAnalytics,ImageAnalyticsGraph |
| image_analytics_label | The label file for tensor flow. Not needed if simulation is 1. Or if the server is not providing ImageAnalyticsService. | labels/mscoco_label_map.pbtxt |
| image_analytics_model_dir | The model directory for tensor flow. Not needed if simulation is 1. Or if the server is not providing ImageAnalyticsService. | models/ssd_inception_v2_coco_2017_11_17/saved_model |

README.md 12/5/2018

| Config | Definition | Default |
|-------------------|---------------------------------|----------------|
| tracker | The tracker server | localhost:1099 |
| rmi_registry_port | The server rmi registry port | 1000 |
| rmi_registry_host | The server rmi registry host/IP | localhost |

Client

File: server.config.properties

| Config | Definition | Default |
|-------------------|------------------------------------------------------|----------------|
| rmi_registry_port | Callback RMI Registry Port | 1088 |
| rmi_registry_host | Callback RMI Registry Host/IP | localhost |
| trackers | Tracker servers to find servers. Comma seperated (,) | localhost:1099 |

Run

Run Tracker

```
Go to bin\tracker and run java -jar tracker.jar in command line / terminal

Go to bin\server and run java -cp server.jar;xchart-3.5.2.jar Server for windows in command line. Run java -cp server.jar:xchart-3.5.2.jar Server for linux in terminal

Go to bin\client and run java -jar client.jar in command line / terminal
```